



Cleanup Instructions for Small Mercury Spills


Michele Wiens, Patti Dods

Introduction

Exposure to the small amount of mercury found in common household devices, such as fever thermometers, thermostats, or fluorescent light bulbs, is not likely to cause serious health problems. Humans are frequently exposed to greater quantities of mercury, much of it methyl mercury, through diet. Nevertheless, all mercury spills, regardless of quantity, should be treated seriously and cleaned up correctly.

When liquid mercury is spilled, it forms droplets. These droplets then evaporate and create a vapour that is odourless and colourless. Mercury is toxic to the human nervous system and exposure to the vapour may result in adverse health effects, if exposure is prolonged or high levels of mercury are present in the air. Small children and developing fetuses are most susceptible to the adverse effects of mercury.

The cleanup recommendations in this document are based on best management practices used by environmental health practitioners. They are derived from the experiences of individuals at the BC Centre for Disease Control, from guidelines written by other jurisdictions and those provided by Environment Canada.¹



Household sources of mercury may include^{2, 3}:

- thermometers, thermostats, barometers, electrical switches;
- medical equipment;
- light bulbs, including: fluorescent, high intensity, mercury vapor, high-pressure sodium, and metal halides;
- clock pendulums;
- toys and cards that light up or make noise;
- batteries^a;
- mercury brought home from work.

^a The only batteries still containing mercury are button-cell batteries. These may be found in watches, calculators and items like toys, cards or shoes that light up or make noise.

Small spills may be safely cleaned up by homeowners if the cleanup is done properly. Small spills are considered to be:

- a few milligrams to 3 grams^b;
- confined to a small area;
- on a hard surface such as tile, linoleum, or wood;
- on a small porous item that can be easily disposed of.

If there is any uncertainty involving your ability to clean up a mercury spill, contact your local health authority for advice. If the mercury spill involves a large area, is in cracks and crevices or other difficult to clean places, or is on items such as wall-to-wall carpeting or upholstery, or has been spread around, tracked throughout the house or involves difficult-to-clean items, it is recommended that you contact a contractor skilled in mercury cleanup. Any spill larger than one tablespoon should be reported to the proper authority; professional assistance is required to ensure a thorough cleanup.

When mercury-containing devices are broken, such as fluorescent bulbs, mercury may not be visible. The broken glass should still be treated as a hazard. Procedures, as outlined in **Step 5** under **Cleanup procedures**, should be followed.

After a mercury spill

- DO NOT use a vacuum cleaner to clean up mercury. Vacuuming a mercury spill will increase the mercury vapour in the air and increase the likelihood of human exposure. Any vacuum cleaner used for cleanup will become contaminated and will need to be discarded as hazardous waste.
- DO NOT use a broom to clean up mercury. The broom will break the mercury into smaller droplets and spread them around a larger area, making it hard to find and pick up.
- DO NOT pour mercury down a drain. This could contaminate the plumbing system and the sewage disposal system.

^b Most household spills will likely be from products that contain a few milligrams to 3.0 grams of mercury. A broken mercury fever thermometer may release 0.5 to 1.5 grams in a spill.⁴

- DO NOT walk around the house in shoes or clothes that may have become contaminated with mercury.
- DO NOT wash mercury-contaminated items in a washing machine. Mercury may contaminate the machine and pollute your septic system.
- DO NOT throw mercury or contaminated items in the garbage – mercury may be emitted as a vapour from landfill sites or from waste incinerators.

Immediately following a small mercury spill

1. Check to see if mercury was splashed on any person or their clothing. If so, carefully remove all contaminated clothing, including shoes, and place in a sealed bag (double- or triple-wrapped) before leaving the spill area. Mercury on the skin should be carefully wiped off with a damp paper towel and towel also be placed in the plastic bag.
2. Keep all children and pets away from the spill.
3. If any mercury was ingested, contact your regional poison control centre.
4. Close doors leading to other indoor areas.
5. Ventilate the spill area to the outdoors if possible.
6. Turn off any ventilation that could circulate air from the spill site to other areas of the structure. This may involve turning down heaters or air conditioners and turning off fans.
7. Turn down the thermostat in order to minimize mercury vaporisation.
8. Stop the spread of mercury by blocking the spill-off with rags. Prevent mercury droplets from entering cracks or rolling under cabinets and appliances.

Preparing for cleanup of mercury spill

1. Assemble the following cleanup supplies:
 - rubber gloves, protective eyewear, or safety glasses
 - clothing and shoes that can be worn and later discarded
 - eye dropper

- large trash bags
 - large tray or box
 - plastic bags with a zipper seal
 - paper towels, facial tissues, or toilet paper
 - rags
 - tape – duct, masking, or packing
 - stiff paper
 - rubber squeegee
 - plastic dust pan
 - wide-mouth plastic containers with lids
 - flashlight
 - tweezers
 - sharp knife
 - commercially available mercury spill kit (optional)
 - vinegar and peroxide (for wiping with swab for residual cleanup – see item 7 below)
2. Change into old clothing and shoes that can be discarded if they become contaminated.
 3. Remove all jewellery; mercury may bond with the metal.
 4. Put on rubber gloves and safety glasses.

Cleanup procedures for a mercury spill

Hard surfaces

1. Using stiff paper, cardboard, or a rubber squeegee, push the mercury beads together from the outside of the spill towards the middle of the spill. Gently push the beads onto a plastic dust pan or draw them into an eye dropper.
2. Very carefully pour the mercury droplets into a wide-mouth container and secure the lid.
3. Use a flashlight to check for any remaining mercury droplets that may have been missed.
4. Use the sticky side of tape to pick up any droplets that could not be picked up with the cardboard. Place the tape on a paper towel, fold, and place in a plastic bag that can be sealed.
5. If the mercury spill involves broken glass, carefully pick up the glass pieces using tweezers. Place the glass pieces on the paper towel, fold, and place in a sealed plastic bag. Small pieces of

glass can be picked up using sticky tape, such as duct tape.

6. Pour or transfer mercury over a large tray or box lined with plastic wrap to prevent spillage. Mercury's high density and smoothness cause it to roll quickly.
7. Residual mercury can be removed by wiping with a vinegar-soaked swab (followed by peroxide if available). The swabs should then be placed in an air-tight container or sealable bag.
8. Dispose of all items that may have been contaminated with mercury. Supplies used for cleanup, as well as any contaminated clothing, shoes, and gloves, should be placed in garbage bags and sealed with tape. Contaminated items should be cleaned or disposed of in accordance with the regulations in your province or territory (see following section). Contact the local office of the Ministry/Department of Environment for further information on disposal.
9. Using an alkaline soap, thoroughly wash your hands, as well as any other body parts that may have come into contact with the mercury.

If you are on a city sewer, your local wastewater treatment plant can handle small amounts of mercury from rinsing the skin. **HOWEVER**, if you are on a septic system, all mercury containing water should be collected and disposed of. If mercury accidentally enters the septic system, stop using it and contact a professional waste contractor.

Other surfaces and items

Porous items (e.g., clothing, carpets, upholstery)

Cost effectiveness of cleaning vs disposal must be evaluated. It may be necessary to hire a contractor skilled in mercury cleanup if one does not wish to dispose of the carpet or upholstery. In certain situations, it may be desirable to cut out the contaminated section of carpet and replace it. Use a sharp knife to cut the contaminated areas away from the uncontaminated area.

- Carefully fold the contaminated item so that the mercury is trapped inside it. Place it in a plastic trash bag and seal with tape.
- Throw away the knife, gloves, and any other contaminated items by placing them in another

large trash bag and sealing with tape. Dispose of the contaminated section in accordance with any applicable regulations.

It may be very difficult to rid all mercury from carpeting, as it may collect in the carpet backing, making it inaccessible for cleanup. If you choose to attempt to clean carpeting following a mercury spill, it is strongly suggested that following cleanup, you have the carpet tested for levels of mercury vapours by contractors skilled in mercury cleanup.

Plumbing (e.g., spills in sink drains)

Working over a tray or bucket, remove the sink trap. It is preferable to place the contaminated trap in a sealed plastic bag. If the old trap is not discarded, the contents of the trap should be poured into a wide-mouth, sealable jar and disposed of. The trap should then be thoroughly washed. Disposal of the trap or its contents should be done in accordance with any local or provincial/territorial regulation.

Disposal

- Make sure that all bags with contaminated items and mercury are double or triple wrapped. Label these plastic bags "*Elemental Mercury: Hazardous Waste.*"
- Label any containers with contaminated washing water in the same fashion.
- Contact your municipal waste department for further disposal instructions.

Acknowledgements

We would like to thank the following individuals for their valuable input and review of the draft document: Ray Copes, Rob Gair, Debra Kent, Bryan Levia, Raymond Li, Nick Losito, and Gordon Mowat.

Follow-up

- Mercury may have seeped into porous surfaces and be impossible to remove. If this is the case, seal with epoxy paint or another sealing agent.
- Continue to ventilate the area with outside air using fans for a minimum of two days if possible. In an office building increase the air exchange rate for one day.

Testing Post Cleanup

If any uncertainty remains as to the effectiveness of the mercury cleanup, it is possible to test for mercury residue in the air using a portable mercury vapour analyser. Consult your local yellow pages for companies that offer testing of mercury levels in indoor air.

A level of $0.2 \mu\text{g}/\text{m}^3$ should be protective of human health.⁵ This should be used as an average concentration in the breathing zone of building occupants, which is well below the allowable occupational limit. Local occupational health and safety authorities can be consulted for any enforceable work place limits. The American Conference of Governmental Industrial Hygienists (ACGIH) threshold limit value (TLV) over an eight-hour period is $25 \mu\text{g}/\text{m}^3$.⁶

If you have any questions regarding the cleanup of small mercury spills, contact your local health authority.

References

1. Environment Canada. Cleaning up small mercury spills. Gatineau, QC; [updated Apr 26, 2012]; Available from: <http://www.ec.gc.ca/mercure-mercury/default.asp?lang=En&n=D2B2AD47-1>.
2. New Jersey State Department of Health and Senior Services. Guidelines for the safe clean-up of mercury spilled in the home. 1996 Jan [cited 2006 Dec 15]; Available from: URL: <http://www.state.nj.us/health/surv/documents/merchome.pdf>.
3. Environment Canada. Products that contain mercury. Gatineau, QC: Environment Canada; [updated Aug 31, 2012]; Available from: <http://www.ec.gc.ca/mercure-mercury/default.asp?lang=En&n=72C0CC0E-1>.
4. Prince Edward Island Department of Fisheries Aquaculture and Environment. Guidelines for the safe clean-up of household mercury spills. Charlottetown, PE. Available from: http://www.gov.pe.ca/photos/original/fae_mercury.pdf.
5. Agency for Toxic Substances and Disease Registry. Toxicological profile for mercury. Atlanta, GA: U.S. Department of Health and Human Services, Centers for Disease Control, Toxic Substances Portal; 1999 Aug. Available from: <http://www.atsdr.cdc.gov/substances/toxsubstance.asp?toxid=24>.
6. American Conference of Governmental Industrial Hygienists (ACGIH). 2010 TLVs and BEIs. Based on the documentation of the threshold limit values for chemical substances and physical agents & biological exposure indices. Cincinnati, OH: ACGIH; 2010 Mar.

This document was produced by the National Collaborating Centre for Environmental Health at the British Columbia Centre for Disease Control in November 2007 and was based on a previous document by Dods and Copes, prepared for the BC Centre for Disease Control, May 2006; revised August 2012.

Permission is granted to reproduce this document in whole, but not in part.

Production of this document has been made possible through a financial contribution from the Public Health Agency of Canada through the National Collaborating Centre for Environmental Health.

Photo credits: Mark Evans; licensed through iStockphoto

ISBN: 978-0-9784317-0-9

© National Collaborating Centre for Environmental Health 2012

400 East Tower
555 W 12th Avenue
Vancouver, BC V5Z 3X7
Tel.: 604-707-2445
Fax: 604-707-2444
contact@nceh.ca



National Collaborating Centre
for Environmental Health
Centre de collaboration nationale
en santé environnementale

To provide feedback on this document, please visit www.nceh.ca/en/document_feedback